

How to make changes to KOP configuration

This guide will show you how to make changes to the KOP configuration.

Contents:

- [Configuration changes to KOP \(web app\) and WildFly](#)
- [Configuration changes to MySQL, Redis, and sshd](#)
- [Related articles](#)

Configuration changes to KOP (web app) and WildFly

1. How to make changes in the **KOP configuration**?
 - a. Within the KOP container, edit configuration files located under **\$(KIUWAN_VOL)/deployconfig/kiuwan**
 - b. Deploy Kiuwan (see below point #3)
2. How to make changes in the **Wildfly configuration**?
 - a. Within the KOP container, edit configuration files located under **\$(KIUWAN_VOL)/deployconfig/wildfly**
 - b. Deploy Kiuwan (see below point #3)
3. How to deploy Kiuwan (after configuration changes)?
 - a. Within the docker server:
 - i. `cd <KIUWAN_VOL>/koptools (KIUWAN_VOL as set in settings.custom)`
 - ii. `./redeployKiuwan.sh`

Configuration changes to MySQL, Redis, and sshd

1. Can I make changes to the configuration of MySQL, Redis, and SSHD?
 - a. Yes, you can (although Kiuwan Docker is presumably configured to suit your needs)
 - b. Changes can only be done within the Docker container
 - c. To change the **MySQL** configuration
 - i. `supervisorctl stop wildfly`
 - ii. `supervisorctl stop mysql`
 - iii. edit **mysqld.cnf** located at **<KIUWAN_VOL>/configurations/etc/mysql/mysqld.conf.d**
 - iv. `supervisorctl start mysql`
 - v. `supervisorctl start wildfly`
 - d. To change the **Redis** configuration
 - i. `supervisorctl stop wildfly`
 - ii. `supervisorctl stop redis`
 - iii. edit **redis.conf** located at **<KIUWAN_VOL>/configurations/etc/redis**
 - iv. `supervisorctl start redis`
 - v. `supervisorctl start wildfly`
 - e. To change the **SSHD** configuration
 - i. after making any change to sshd configuration, you must **persist docker image** :
 - `logout from the container and log in to docker server`
 - `execute: commit <kop docker name> <kop docker image>`
 - NOTE: run 'docker ps' to get NAMES and IMAGE values of your KOP container

Related articles

- [How to change passwords after KOP container is built](#)
- [How to obtain KOP log files](#)
- [How to check status and manage KOP services](#)
- [How to change email configuration](#)
- [How to make changes to KOP configuration](#)