

Installed version	This column shows the version name of the current installed versions (both for Kiuwan core and clients).
Last available version	This column shows the latest available version of Kiuwan core and clients.
Status	When a new version is detected this column will indicate that an upgrade is available.
Minimum Kiuwan On-Premises version needed to upgrade clients	If your current Kiuwan Core version is less than this version, new versions of Kiuwan On-Premises clients will not be available for your installation anymore. If you want to upgrade, it is mandatory to perform a full upgrade. See Upgrade: full mode section for more information.

Command Line Interface mode

You can also check your current Kiuwan On-Premises core version by running this command on a Kiuwan front instance host:

```
cat [VOLUMES_DIR]/data-shared/publicData/current.version
```

Upgrade modes

You can upgrade only Kiuwan On-Premises clients or perform a full upgrade to your Kiuwan On-Premises installation.



Both clients only and full modes will update changes made in the current configuration that have not been already applied, but keep in mind that new configuration properties will only be available after performing a full upgrade. Default configuration values will be used when starting a new version of Kiuwan services.

Clients only mode

You can choose to upgrade only Kiuwan On-Premises clients as long as their latest versions are compatible with your currently installed Kiuwan core. The upgrade process will check this for you and stop the upgrade if your current Kiuwan core is not compatible with the latest available clients.



Do not mix up what a Kiuwan On-Premises client version is. These are different concepts:

- Client versions stored in your Kiuwan On-Premises servers: these are the versions that your Kiuwan On-Premises server provides to be downloaded and installed on your CI systems, development computers, etc. These versions are those shown in the System Administration Console.
- Client versions installed in your company's laptops, CI systems, etc.: these are the versions that were installed after your first Kiuwan On-Premises installation or subsequent upgrades. Once you upgrade your installation client versions, your company's computers may have old versions of Kiuwan On-Premises clients. The following steps address how to upgrade these as well.

Kiuwan On-Premises clients are those Kiuwan products that your Kiuwan On-Premises servers will provide to your users:

- Kiuwan Local Analyzer
- Kiuwan Engine
- Kiuwan for developers IDE plugins or extensions (Eclipse, JetBrains, Visual Studio and Visual Studio Code).

There are more Kiuwan clients that you may need to upgrade, but are provided by external sources and you should follow the standard upgrade procedure of their platform. Note that these products latest versions may be only compatible with the latest available Kiuwan On-Premises core services:

- Kiuwan Jenkins plugin: downloadable from the Jenkins plugin repository.
- Kiuwan Microsoft TFS Azure extension: downloadable through the Azure DevOps marketplace.

Choose this upgrade mode when:

- New versions of Kiuwan On-Premises clients are available.
- You want to upgrade your installation to make your Kiuwan On-Premises servers provide the latest available versions of each client.
- You want to keep your Kiuwan services untouched.

Full mode

The full mode upgrade will upgrade both Kiuwan On-Premises clients and Kiuwan core services.

Keep in mind that when choosing this mode you should always download the latest kiuwan-cluster version available. The latest version is always accessible through this link: <https://static.kiuwan.com/download/onpremise/kiuwan-cluster.tar.gz>.

Choose this upgrade mode when:

- You want to upgrade your Kiuwan On-Premises clients but your Kiuwan core services version is not compatible with the latests client versions.
- You want to have the latest fixes and features available in Kiuwan.



You can directly update your Kiuwan On-Premises installation guide from any version to the latest available version.

Upgrade: common steps

Either if you are upgrading only clients or performing a full upgrade, you must follow these steps before starting the upgrade process.

Step 1: backup your current volumes

Just in case an unexpected error occurs during the upgrade process, it is convenient that you backup all your volumes before proceeding.

You should copy all files under these directories and keep the copy in a safe place:

- [VOLUMES_DIR]/config-shared
- [VOLUMES_DIR]/data-local
- [VOLUMES_DIR]/data-shared

Step 2: check clients upgrade bypass configuration

To make sure that your current configuration is not ignoring new available clients, you should check if "kiuwan.clients.update" is set in the following file:

- [VOLUMES_DIR]/config-shared/globalConfig/globalConfig.properties

Locate the key "kiuwan.clients.update" at the end of the file and make sure it is set to true:

```
kiuwan.clients.update=true
```

When the flag is set to true, all Kiuwan clients will be updated as long as a new version is available.

Step 3: check the status of Kiuwan On-Premises infrastructure

To upgrade Kiuwan On-Premises it is mandatory that at least these elements of the provided (or externalized if you chose to use your own) infrastructure are up and running:

- MySQL
- Redis cluster

If you have run any of the provided scripts that stop this infrastructure elements (or your own instances are stopped if externalized), please make sure you start them before proceeding to upgrade.

Upgrade: clients only mode

Note that it is **safe to update Kiuwan On-Premises clients WITHOUT stopping any of the provided services or containers**, but make sure you have checked the Step 3 of the common steps before proceeding.

Step 1: run the clients upgrade

Open a terminal to your Kiuwan On-Premises host and locate the kiuwan-cluster tool you used to install Kiuwan On-Premises.

Change the directory to where the tool was untared (this directory is referred as [INSTALLER_DIR] in the [Kiuwan On-Premises Distributed Installation Guide](#)).

Once the current directory is [INSTALLER_DIR], execute this command:

```
sudo ./update-clients.sh
```

Upgrade: full mode

Note that a full upgrade will update your Kiuwan On-Premises clients as well, so there is no need to run the clients upgrade when performing a full upgrade.

This process will stop all Kiuwan services. This means that during the upgrade process:

- Users will not be able to access Kiuwan On-Premises web application.
- No analysis can be run while performing the upgrade process. Make sure you pause any automated task running analyses in your Kiuwan On-Premises installation.

Once the upgrade is finished, all services will be automatically restarted and you will be able to access Kiuwan On-Premises after a while.

Step 1: keep your old kiuwan-cluster installer

Your current installer may be needed in order to perform some maintenance tasks. It is usually a better idea to keep your current kiuwan-cluster version just in case you need to access it.

It is enough just to keep the already existing folder where you untared your current kiuwan-cluster as new versions will always be untared to a different folder.

If the old version of kiuwan-cluster is needed through the upgrade process, its path will be referred to as [INSTALLER_DIR_OLD].

For example, if you are upgrading from Kiuwan On-Premises 2.8.1910.1, your folders will look like this:

- [INSTALLER_DIR_OLD]: /home/user/kiuwan-cluster_master.265-2.8.1910.1
- [INSTALLER_DIR]: /home/user/kiuwan-cluster_master.XXX-2.8.YYMM.Y (you will create this folder in the next steps).

Step 2: download kiuwan-cluster latest version

In order to upgrade to the latest versions of Kiuwan On-Premises images you need to download the latest version of the installation tool. Run this in your Kiuwan On-Premises host:

```
wget https://static.kiuwan.com/download/onpremise/kiuwan-cluster.tar.gz
```

This will download the latest available installation tool to the current directory.

Step 3: untar kiuwan-cluster

Once downloaded, you should untar the provided gz file:

```
tar xvpzf kiuwan-cluster.tar.gz
```

This will untar the installation tool to a folder with extended version information of the tool. For example:

/home/user/kiuwan-cluster_master.XXXX-2.8.YYMM.V

This folder will be referred to as [INSTALLER_DIR] throughout the following steps.

Step 4: update kiuwan-cluster volumes and user-content configuration

Copy the volumes configuration from the old to the new kiuwan-cluster folders:

```
cp [INSTALLER_DIR_OLD]/config/volumes.properties [INSTALLER_DIR]/config/volumes.properties
```

This will configure the volumes location in the new kiuwan-cluster.

Then copy the old user-content folder to the new kiuwan-cluster user-content folder:

```
cp -r [INSTALLER_DIR_OLD]/user-content [INSTALLER_DIR]
```

This will keep track of the latest license and certificates you configured with the previous kiuwan-cluster:

Step 5: check if your available commands meet the needed prerequisites

This step is needed just in case you installed your old Kiuwan On-Premises version not meeting the needed minimum requirements for the needed tools (check [Installation requirements](#) section for a complete list of required tools).

In order for the upgrade process to work, the minimum tool versions requirements must be met.

Run the following script and check the "**Checking commands**" section:

```
cd [INSTALLER_DIR]
sudo ./check-prerequisites.sh
```

In case you see that the command versions requirements are not met (either because a command is not available or because its version is not supported), please update your system until the marked requirements are met.



You need only to check the "Checking command" section. It is OK if you see that some of the ports or the docker network are in use, as at this point your Kiuwan On-Premises services should be still running.

You can run the check-prerequisites tool as many times as needed.



Do not continue to the next step until all TOOL VERSIONS requirements are met or your Kiuwan On-Premises installation stability could be compromised.

Step 6: check specific upgrade steps

First, identify which Kiuwan On-Premises version you have currently installed. Refer to [Checking for new versions](#) section for details on how to check it.

The [Specific version upgrade notes](#) page shows which versions need special upgrade steps.

If your current Kiuwan On-Premises core version needs a special upgrade process, follow the specific upgrade steps for your current Kiuwan On-Premises core version shown in the [Specific version upgrade notes](#) page.

Step 7: run the upgrade process

NOTE: you should **IGNORE** this step if you come from a specific upgrade process.

If your current Kiuwan On-Premises core version is not listed in the [Specific version upgrade notes](#) page, change the directory to [INSTALLER_DIR] and execute this command:

```
sudo ./update-full.sh
```

This will run the upgrade process in full mode.

Step 8: load balancer manual configuration (optional)

Kiuwan On-Premises installation tool will not update automatically your load balancer configuration, so changes in this file must be made manually. Refer to the [Specific version upgrade notes](#) page for information on what changes have been made in this element if you want to keep your installation up to date with the latests features added in the load balancer configuration.



Note that this is an optional step. If you are happy with your current configuration or you want to maintain your own custom configuration, you can safely ignore it.

In case you are running the default configuration, you can safely overwrite your configuration, but REMEMBER TO UPDATE "kiuwanDomain" variable to point to your specific Kiuwan On-Premises domain:

```
cp ./volumes/config-shared/ApacheLoadBalancer/conf/httpd.conf [VOLUMES_DIR]
/config-shared/ApacheLoadBalancer/conf/httpd.conf
```

Once the file has been overwritten, edit it and change this line in [VOLUMES_DIR]/config-shared/ApacheLoadBalancer/conf/httpd.conf:

```
Define kiuwanDomain kiuwan.onpremise.local
```

It should point to your specific domain.

Once the configuration changes have been made, you should restart the apacheloadbalancer container:

```
cd [INSTALLER_DIR]/docker
sudo ./stop-infrastructure.sh apacheloadbalancer
sudo ./start-infrastructure.sh apacheloadbalancer
```

In case you have externalized the Apache load balancer service, remember to restart it after modifying its configuration.

Checking your Kiuwan On-Premises clients installations after upgrading

Once the update process is finished, all the published clients in your Kiuwan On-Premises installation will be ready to be downloaded. Check the specific client guide to see how to upgrade each client installation:

- Kiuwan Local Analyzer: upgrades automatically when started whenever your Kiuwan On-Premises servers provide a new version to download.
- Kiuwan Engine: upgrades automatically from Kiuwan Local Analyzer, as long as your Kiuwan On-Premises servers provide a new version and your engine is not frozen (see [Engine](#) documentation for more information on this topic).
- Kiuwan for developers:
 - Eclipse: check [Kiuwan for Developers for Eclipse-based IDEs](#) user guide.
 - JetBrains: check [Kiuwan for Developers for JetBrains](#) user guide.
 - Microsoft Visual Studio: check [Kiuwan for Developers for Microsoft Visual Studio](#) user guide.
 - Microsoft Visual Studio Code: check [Kiuwan for Developers for Microsoft Visual Studio Code](#) user guide.
- Kiuwan Jenkins plugin: check [Jenkins plugin \(old\)](#) user guide.
- Kiuwan TFS extension: check [Microsoft TFS-Azure DevOps Extension](#) user guide.